

# Finishing Up

(This is the same as [Release results](#))

If you'd like to export results out of the capsule, you must release them from your virtual machine.

First, switch the VM to secure mode in the Portal interface.

Second, open a terminal in the capsule, navigate to the secure volume by typing:

```
cd /media/secure_volume
```

Suppose the file you'd like to release is at `/home/demouser/demo/r/Rplots.pdf`

You can prepare the result data for release by first adding it to the release list:

```
releaseresults add /home/demouser/demo/r/Rplots.pdf
```

Repeat using this command if you have other files to add.

Finally, to complete the release of your data, type:

```
releaseresults done
```

The files will be delivered via email. You will receive them in the email that you registered for the HTRC Analytics account. The email link will be live for 12 hours.

## Shut Down the VM

Go back to [HTRC Analytics](#), go to "Data Capsules" and click on the "Stop Capsule" button to shut down the VM you'd like to shut.

### Data Capsules

Data Capsule ID	Status	Actions
<a href="#">4182c5cf-0855-433e-af56-0da126a2cb15</a>	Status: MAINTENANCE Mode: RUNNING	<a href="#">Stop Capsule</a> <a href="#">Switch to Secure Mode</a> <a href="#">Delete Capsule</a>

To log in to a Data Capsule, you can use a VNC client when the capsule is in either Secure or Maintenance mode. SSH login is also available, but only when in Maintenance mode and not when the capsule is in Secure mode. Get VNC and SSH login information by clicking the 'Data Capsule ID' link above. For more information, please refer the [documentation](#).

## Delete the VM

If you do not need the capsule any more, you can delete it. On HTRC Analytics, navigate to "Data Capsules", click on the "Delete Capsule" button next to the virtual machine you want to delete.

## Data Capsules

Data Capsule ID	Status	Actions
<a href="#">4182c5cf-0855-433e-af56-0da126a2cb15</a>	Status: MAINTENANCE Mode: RUNNING	<a href="#">Stop Capsule</a> <a href="#">Switch to Secure Mode</a> <a href="#">Delete Capsule</a>

To log in to a Data Capsule, you can use a VNC client when the capsule is in either Secure or Maintenance mode. SSH login is also available, but only when in Maintenance mode and not when the capsule is in Secure mode. Get VNC and SSH login information by clicking the 'Data Capsule ID' link above. For more information, please refer the [documentation](#).